

Transfer Mastro to a New Computer (Steps)

Prerequisites

You must have:

- your email address
- your license number

If your email address has changed, please inform us, since the license is associated with it.

To check your computer's processor type:

Settings → System → About your PC

1) Retrieve the data from the old computer

Option A — Contents of the folder “C:\ProgramData\Mastro Software\Mastro”

- Open Mastro on the old computer.
- Menu: Tools → Data Management
- Click *Show Data Directory*
- Select all files and folders (CTRL + A)
- Copy them to an external drive (external disk or USB key)

Option B — Copy the entire folder “C:\ProgramData\Mastro Software\Mastro”

You may also open a Windows File Explorer window (icon: yellow folder), then type in the address bar:

C:\ProgramData\Mastro Software

Then select the entire **Mastro** folder and copy it to your external drive.

Name the backup folder

Name the folder, for example:

Mastro_backup_7.7_2025-01-01

Including the software version and the date is useful if you keep multiple backups.

2) Install Mastro on the new computer

(.NET Framework 3.5 + latest Mastro installer)

Windows 10 (x86 processor)

Install Microsoft .NET Framework 3.5:

<https://dotnet.microsoft.com/download/dotnet-framework/net35-sp1>

(dotnet.microsoft.com in Bing)

Windows 11 (x86 processor)

Enable .NET Framework 3.5

1. Click in the Search box on the taskbar.
 2. Type **Run** and open the *Run* application.
 3. In the Run dialog, type:
optionalfeatures
 4. Click OK.
 5. In *Windows Features*, find **.NET Framework 3.5 (includes .NET 2.0 and 3.0)**.
 6. Click the + to expand.
 7. Check:
 - WCF HTTP Activation
 - WCF Non HTTP Activation
 8. Click OK.
-

Windows 11 (ARM processor)

1. Enable .NET Framework 3.5 (see above “Enable .NET Framework 3.5”).
 2. Set ARM emulation to **Secure Emulation** (see appendix – p.4).
-

Download the Mastro installer

- **Mastro Standard:**

https://mastroapp.com/download/mastro_installer_standard.exe

- **Mastro Expert:**

https://mastroapp.com/download/mastro_installer_expert.exe

3) Transfer the data to the new computer

1. Open Mastro on the new computer.
2. Menu: Tools → Data Management
3. Click *Show Data Directory*
4. Replace the existing files with those from your backup.

If you used, in the step “Retrieve the data from the old computer”...

- *Option A*

Overwrite the contents of the **Mastro** folder with the contents of your backup (i.e., open the Mastro folder and replace all files and subfolders with those from your copy).

- *Option B*

Overwrite the entire **Mastro** folder with your backed-up Mastro folder (i.e., delete or rename the existing folder, then copy your backed-up Mastro folder in its place).

Important Note

Mastro’s data is located under:

C:\ProgramData\Mastro Software

This is a hidden folder by default in Windows.

This folder is different from the folder containing the program executable, located under:

C:\Program Files (x86)\Mastro

5. Restart Mastro.
-


Appendix

Windows 11 ARM – Emulation Settings

Go to:

C:\Program Files (x86)\Mastro

Right-click **Mastro.exe** → Properties



Next, in the properties window, find "emulation" and set it to "Secure Emulation."

Screenshot generated from a Windows 11 on VMWare Fusion